

Notes on pseudopotential generation

Paolo Giannozzi

Università di Udine and IOM-Democritos, Trieste

URL: <http://www.fisica.uniud.it/~giannozz>

July 25, 2012

Contents

1	Introduction	1
1.1	Who needs to generate a pseudopotential?	1
1.2	About similar work	2
1.3	Pseudopotential generation, in general	2
2	Step-by-step Pseudopotential generation	3
2.1	Choosing the generation parameters	3
2.1.1	Exchange-correlation functional	3
2.1.2	Valence-core partition	4
2.1.3	Electronic reference configuration	5
2.1.4	Nonlinear core correction	6
2.2	Type of pseudization	7
2.2.1	Pseudization energies	7
2.2.2	Pseudization radii	8
2.2.3	Choosing the local potential	8
2.3	Generating the pseudopotential	9
2.4	Checking for transferability	10
3	A worked example: Ti	10
3.1	Single-projector, norm-conserving, no semicore	11
3.1.1	Generation	11
3.1.2	Testing	15
3.2	Single-projector, norm-conserving, with semicore states	19
3.3	Testing in molecules and solids	22
A	Atomic Calculations	22
A.1	Nonrelativistic case	22
A.1.1	Useful formulae	23
A.2	Fully relativistic case	23
A.3	Scalar-relativistic case	23
A.4	Numerical solution	24

1 Introduction

When I started to do my first first-principle calculation (that is, my first²-principle calculation) with Stefano Baroni on CsI under pressure (1985), it became quickly evident that available pseudopotentials (PP's) couldn't do the job. So we generated our own PP's. Since that first experience I have generated a large number of PP's and people keep asking me new PP's from time to time. I am happy that "my" PP's are appreciated and used by other people. I don't think however that the generation of PP's is such a hard task that it requires an official (or unofficial) PP wizard to do this. For this reason I want to share here my (little) experience.

These notes are written in general but having in mind the capabilities of the `atomic` package, included in the QUANTUM ESPRESSO distribution (<http://www.quantum-espresso.org>). `atomic`, mostly written and maintained by Andrea Dal Corso and others, is the evolution of an older code I maintained for several years. `atomic` can generate both Norm-Conserving (NC) [1] and Ultrasoft (US) [2] PP's, plus Projector Augmented Waves (PAW) [3] sets. It allows multiple projectors, full relativistic calculations, spin-split PP's for spin-orbit calculations. For the complete description of the input of `atomic`, please refer to files `INPUT_LD1.txt` and `INPUT_LD1.html`.

1.1 Who needs to generate a pseudopotential?

There are at least three well-known published sets of NC-PP's: those of Bachelet, Hamann, and Schlüter [4], those of Gonze, Stumpf, and Scheffler [5], and those of Goedecker, Teter, and Hutter [6]. Moreover, all major packages for electronic-structure calculations include a downloadable table of PP's. One could then wonder what a PP generation code is useful for. The problem is that sometimes available PP's will not suit your needs. For instance, you may want:

- a better accuracy;
- PP's generated with some exotic or new exchange-correlation functional;
- a different partition of electrons into valence and core;
- "softer" PP's (i.e. PP that require a smaller cutoff in plane-wave calculations);
- PP's with a core-hole for calculations of X-ray Adsorption Spectra;
- all-electron wavefunctions reconstruction (requires the knowledge of atomic all-electron and pseudo-orbitals used in the generation of PP's);

or you may simply want to know what is a PP, how to produce PP's, how reliable they are.

1.2 About similar work

There are other PP generation packages available on-line. Those I am aware of include:

- the code by José-Luís Martins *et al.*[7]:
<http://bohr.inesc-mn.pt/~jlm/pseudo.html>
- the fhi98PP package[8]:
<http://www.fhi-berlin.mpg.de/th/fhi98md/fhi98PP>
- the OPIUM code by Andrew Rappe *et al.*[9]:
<http://opium.sourceforge.net/>
- David Vanderbilt’s US-PP package [2]:
<http://www.physics.rutgers.edu/~dhv/uspp/index.html>.

Other codes may be available upon request from the authors.

Years ago, it occurred to me that a web-based PP generation tool would have been nice. Being too lazy and too ignorant in web-based applications, I did nothing. I recently discovered that Miguel Marques *et al.* have implemented something like this: see <http://www.tddft.org/programs/octopus/pseudo.php>.

1.3 Pseudopotential generation, in general

In the following I am assuming that the basic PP theory is known to the reader. Otherwise, see Refs.[1, 4, 7, 8, 9] and references quoted therein for NC-PP’s; Refs.[2, 3] for US-PP’s and PAWsets. I am also assuming that the generated PP’s are to be used in separable form [10] with a plane-wave (PW) basis set.

The PP generation is a three-step process. First, one generates atomic levels and orbitals with Density-functional theory (DFT). Second, from atomic results one generates the PP. Third, one checks whether the reesulting PP is actually working. If not, one tries again in a different way.

The first step is invariably done assuming a spherically symmetric self-consistent Hamiltonian, so that all elementary quantum mechanics results for the atom apply. The atomic state is defined by the ”electronic configuration”, one-electron states are defined by a principal quantum number and by the angular momentum and are obtained by solving a self-consistent radial Schrödinger-like (Kohn-Sham) equation.

The second step exists in many variants. One can generate ”traditional” single-projector NC-PP’s; multiple-projector US-PP’s, or PAW sets. The crucial step is in all cases the generation of smooth ”pseudo-orbitals” from atomic all-electron (AE) orbitals. Two popular pseudization methods are presently implemented: Troullier-Martins [7] and Rappe-Rabe-Kaxiras-Joannopoulos [9] (RRKJ).

The second and third steps are closer to cooking than to science. There is a large arbitrariness in the preceding step that one would like to exploit in order to get the ”best” PP, but there is no well-defined way to do this. Moreover one is often forced to strike a compromise between transferability (thus accuracy) and hardness (i.e. computer time). These two steps are the main focus of these notes.

2 Step-by-step Pseudopotential generation

If you want to generate a PP for a given atom, the checklist is the following:

- choose the generation parameters:
 1. exchange-correlation functional
 2. valence-core partition
 3. electronic reference configuration
 4. nonlinear core correction
 5. type of pseudization
 6. pseudization energies
 7. pseudization radii
 8. local potential
- generate the pseudopotential
- check for transferability

In case of trouble or of unsatisfactory results, one has to go back to the first step and change the generation parameters, usually in the last four items.

2.1 Choosing the generation parameters

2.1.1 Exchange-correlation functional

PP's must be generated with the *same* exchange-correlation (XC) functional that will be later used in calculations. The use of, for instance, a GGA (Generalized Gradient Approximation) functional together with PP's generated with Local-Density Approximation (LDA) is inconsistent. This is why the PP file contains information on the DFT level used in their generation: if you or your code ignore it, you do it at your own risk.

The `atomic` package allows PP generation for a large number of functionals, both LDA and GGA. Most of them have been extensively tested, but beware: some exotic or seldom-used functionals might contain bugs. Currently, `atomic` does not allow PP generation with meta-GGA (TPSS) or hybrid functionals. For the former, an old version of `atomic`, modified by Xiaofei Wang, is available. Work is in progress for the latter.

Some functionals may present numerical problems when the charge density goes to zero. For instance, the Becke gradient correction to the exchange may diverge for $\rho \rightarrow 0$. This does not happen in a free atom if the charge density behaves as it should, that is, as $\rho(r) \rightarrow \exp(-\alpha r)$ for $r \rightarrow \infty$. In a pseudoatom, however, a weird behavior may arise around the core region, $r \rightarrow 0$, because the pseudocharge in that region is very small or sometimes vanishing (if there are no filled s states). As a consequence, nasty-looking “spikes” appear in the unscreened pseudopotential very close to the nucleus. This is not nice at all but it is usually harmless, because the interested region is really

very small. However in some unfortunate cases there can be convergence problems. If you do not want to see those horrible spikes, or if you experience problems, you have the following choices:

- Use a better-behaved GGA, such as PBE
- Use the nonlinear core correction, which ensures the presence of some charge close to the nucleus.

A further possibility would be to cut the gradient correction for small r (it used to be implemented, but it isn't any longer).

2.1.2 Valence-core partition

This seems to be a trivial step, and often it is: valence states are those that contribute to bonding, core states are those that do not contribute. Things may sometimes be more complicated than this. For instance:

- in transition metals, whose typical outer electronic configuration is something like (n = main quantum number) $nd^i(n+1)s^j(n+1)p^k$, it is not always evident that the ns and np states (“semicore states”) can be safely put into the core. The problem is that nd states are localized in the same spatial region as ns and np states, deeper than $(n+1)s$ and $(n+1)p$ states. This may lead to poor transferability. Typically, PP's with semicore states in the core work well in solids with weak or metallic bonding, but perform poorly in compounds with a stronger (chemical) type of bonding.
- Heavy alkali metals (Rb, Cs, maybe also K) have a large polarizable core. PP's with just one electron may not always give satisfactory results.
- In some II-VI and III-V semiconductors, such as ZnSe and GaN, the contribution of the d states of the cation to the bonding is not negligible and may require explicit inclusion of those d states into the valence.

In all these cases, promoting the highest core states ns and np , or nd , into valence may be a computationally expensive but obliged way to improve poor transferability. .

You should include semicore states into valence only if really needed: their inclusion in fact makes your PP harder (unless you resort to US pseudization) and increases the number of electrons. In principle you should also use more than one projector per angular momentum, because the energy range to be covered by the PP with semicore electrons is much wider than without. For instance, it may happen that the error on the lattice parameter of a simple metal is larger with a semicore PP than with a valence-only PP.

2.1.3 Electronic reference configuration

This may be any reasonable configuration not too far away from the expected configuration in solids or molecules. As a first choice, use the atomic ground state, unless you have a reason to do otherwise, such as for instance:

- You do not want to deal with unbound states. Very often states with highest angular momentum l are not bound in the atom (an example: the $3d$ state in Si is not bound on the ground state $3s^23p^2$, at least with LDA or GGA). In such a case one has the choice between
 - using one configuration for s and p , another, more ionic one, for d , as in Refs.[4, 5];
 - choosing a single, more ionic configuration for which all desired states are bound;
 - generate PP's on unbound states: requires to choose a suitable reference energy.
- The results of your PP are very sensitive to the chosen configuration. This is something that in principle should not happen, but I am aware of at least one case in which it does. In III-V zincblende semiconductors, the equilibrium lattice parameter is rather sensitive to the form of the d potential of the cation (due to the presence of $p - d$ coupling between anion p states and cation d states [12]). By varying the reference configuration, one can change the equilibrium lattice parameter by as much as 1 – 2%. The problem arises if you want to calculate accurate dynamical properties of GaAs/AlAs alloys and superlattices: you need to get a good theoretical lattice matching between GaAs and AlAs, or otherwise unpleasant spurious effects may arise. When I was confronted with this problem, I didn't find any better solution than to tweak the $4d$ reference configuration for Ga until I got the observed lattice-matching.
- You know that for the system you are interested in, the atom will be in a given configuration and you try to stay close to it. This is not very elegant but sometimes it is needed. For instance, in transition metals described by a PP with semicore states in the core, it is probably wise to chose an electronic configuration for d states that is close to what you expect in your system (as a hand-waiving argument, consider that the $(n + 1)s$ and $(n + 1)p$ PP have a hard time in reproducing the true potential if the nd state, which is much more localized, changes a lot with respect to the starting configuration). In Rare-Earth compounds, leaving the $4f$ electrons in the core with the correct occupancy (if known) may be a quick and dirty way to avoid the well-known problems of DFT yielding the wrong occupancy in highly correlated materials.
- You don't manage to build a decent PP with the ground state configuration, for whatever reason.

NOTE 1: you can calculate PP for a l as high as you want, but you are not obliged to use all of them in PW calculations. The general rule is that if your atom has states up to $l = l_c$ in the core, you need a PP with angular momenta up to $l = l_c + 1$. Angular momenta $l > l_c + 1$ will feel the same potential as $l = l_c + 1$, because for all of them there is no orthogonalization to core states. As a consequence a PP should have projectors on angular momenta up to l_c ; $l = l_c + 1$ should be the local reference state for PW calculations. This rule is not very strict and may be relaxed: high angular momenta

are seldom important (but be careful if they are). Moreover separable PP pose serious constraints on local reference l (see below) and the choice is sometimes obliged. Note also that the highest the l in the PP, the more expensive the PW calculation will be.

NOTE 2: a completely empty configuration ($s^0p^0d^0$) or a configuration with fractional occupation numbers are both acceptable. Even if fractional occupation numbers do not correspond to a physical atomic state, they correspond to a well-defined mathematical object.

NOTE 3: PP could in principle be generated on a spin-polarized configuration, but a spin-unpolarized one is typically used. Since PP are constructed to be transferrable, they can describe spin-polarized configurations as well. The nonlinear core correction is needed if you plan to use PP in spin-polarized (magnetic) systems.

2.1.4 Nonlinear core correction

The nonlinear core correction[11] accounts at least partially for the nonlinearity in the XC potential. During PP generation one first produces a potential yielding the desired pseudo-orbitals and pseudoenergies. In order to extract a “bare” PP that can be used in a self-consistent DFT calculation, one subtracts out the screening (Hartree and XC) potential generated by the valence charge only. This introduces a transferability error because the XC potential is not linear in the charge density. With the nonlinear core correction one keeps a pseudized core charge to be added to the valence charge both at the unscreening step and when using the PP.

The nonlinear core correction *must* be present in one-electron PP’s for alkali atoms (especially in ionic compounds) and for PP’s to be used in spin-polarized (magnetic) systems. It is recommended whenever there is a large overlap between valence and core charge: for instance, in transition metals if the semicore states are kept into the core. Since it is *never* harmful, one can take the point of view that it should always be included, even in cases where it will not be very useful.

The pseudized core charge used in practice is equal to the true core charge for $r \geq r_{cc}$, differs from it for $r < r_{cc}$ in such a way as to be much smoother. The parameter r_{cc} is typically chosen as the point at which the core charge $\rho_c(r_{cc})$ is twice as big as the valence charge $\rho_v(r_{cc})$. In fact the effect of nonlinearity is important only in regions where $\rho_c(r) \sim \rho_v(r)$. Alternatively, r_{cc} can be provided in input, Note that the smaller r_{cc} , the more accurate the core correction, but also the harder the pseudized core charge, and vice versa.

2.2 Type of pseudization

The atomic package implements two different NC pseudization algorithms, both claiming to yield optimally smooth PP’s:

- Troullier-Martins [7] (TM)
- Rappe-Rabe-Kaxiras-Joannopoulos [9] (RRKJ).

Both algorithms replace atomic orbitals in the core region with smooth nodeless pseudo-orbitals. The TM method uses an exponential of a polynomial (see Appendix B); the

RRKJ method uses three or four Bessel functions for the pseudo-orbitals in the core region. The former is very robust. The latter may occasionally fail to produce the required nodeless pseudo-orbital. If this happens, first try to force the usage of four Bessel functions (this is achieved by setting a small nonzero value of the charge density at the origin, variable `rho0`: unfortunately it works only for s states).

Second-row elements N, O, F, $3d$ transition metals, rare earths, are typically “hard” atoms, i.e. described by NC PP’s requiring a high PW cutoff. These atoms are characterized by $2p$ (N, O, F), $3d$ (transition metals), $4f$ (rare earths) valence states with no orthogonalization to core states of the same l and no nodes. In addition, as mentioned in Secs.2.1.2 and 2.1.3, there are cases in which you may be forced to include semicore states in valence, thus making the PP hard (or even harder). In all such cases, one should consider *ultrasoft* pseudization, unless there is a good reason to stick to NC-PP’s. For the specific case of rare earths, however, remember that the problem of DFT reliability preempts the (tough) problem of generating a PP. With US-PP’s one can give up the NC requirement and get much softer PP’s, at the price of introducing an augmentation charge that compensates for the missing charge.

Currently, the `atomic` package generates US-PP’s on top of a “hard” NC-PP. In order to ensure sufficient transferability, at least two states per angular momentum l are required.

2.2.1 Pseudization energies

If you stick to single-projector PP’s (one potential per angular momentum l , i.e. one projector per l in the separable form), the choice of the electronic configuration automatically determines the reference states to pseudize: for each l , the bound valence eigenstate is pseudized at the corresponding eigenvalue. If no bound valence eigenstate exists, one has to select a reference energy. The choice is rather arbitrary: you may try something between other valence bound state energies and zero.

If you have semicore states in valence, remember that for each l only the state with lowest n can be used to generate a single-projector PP. The `atomic` package requires that you explicitly specify the configuration for unscreening in the “test” configuration: see the detailed input documentation.

It is possible to generate PP’s by pseudizing atomic waves, i.e. regular solutions of the radial Kohn-Sham equation, at any energy. More than one such atomic waves of different energy can be pseudized for the same l , resulting in a PP with more than one projector per l (directly produced in the separable form). Note however that the implementation of multiple-projector PP’s is correct for US pseudization: NC pseudization is not properly done (a generalized norm-conservation requirement is not accounted for). US pseudization is achieved by setting different NC and US pseudization radii (see Sec.2.2.2),

2.2.2 Pseudization radii

For NC pseudization, one has to choose, for each state to be pseudized, a NC pseudization radius r_c , at which the AE orbital and the corresponding NC-PP orbital match, with continuous first derivative at $r = r_c$. For bound states, r_c is typically at the

outermost peak or somewhat larger. The larger the r_c , the softer the potential (less PW needed in the calculations), but also the less transferable. The r_c may differ for different l ; as a rule, one should avoid large differences between the r_c 's, but this is not always possible. Also, the r_c cannot be smaller than the outermost node.

A big problem in NC-PP's is how strike a compromise between softness and transferability, especially for difficult elements. The basic question: "how much should I push r_c outwards in order to have reasonable results with a reasonable PW cutoff". has no clear-cut answer. The choice of r_c at the outermost maximum for "difficult" elements (those described in Sec.2.2.1): typically 0.7-0.8 a.u, even less for $4f$ electrons, yields very hard PP's (more than 100 Ry needed in practical calculations). With a little bit of experience one can say that for second-row ($2p$) elements, $r_c = 1.1 - 1.2$ will yield reasonably good results for 50-70 Ry PW kinetic energy cutoff; for $3d$ transition metals, the same r_c will require > 80 Ry cutoff (highest l have slower convergence for the same r_c). The above estimates are for TM pseudization. RRKJ pseudization will yield an estimate of the required cutoff.

For multiple-projectors PP's, the r_c of unbound states may be chosen in the same range as for bound states. Use small r_c and don't try to push them outwards: the US pseudization will take care of softness. US pseudization radii can be chosen much larger than NC ones (e.g. $1.3 \div 1.5$ a.u. for second-row $2p$ elements, $1.7 \div 2.2$ a.u. for $3d$ transition metals), but do not forget that the sum of the r_c of two atoms should not exceed the typical bond length of those atoms.

Note that it is the hardest atom that determines the PW cutoff in a solid or molecule. Do not waste time trying to find optimally soft PP's for element X if element Y is harder than element X.

2.2.3 Choosing the local potential

As explained in Sec. 2.1.3, note 1, one needs in principle angular momentum channels in PP's up to $l_c + 1$. In the semilocal form, the choice of a "local", l -independent potential is natural and affects only seldom-important PW components with $l > l_c$. In PW calculations, however, a separable, fully nonlocal form – one in which the PP's is written as a local potential plus projectors – is used. An arbitrary function can be added to the local potential and subtracted to all l components. Generally one exploits this arbitrariness to remove one l component using it as local potential. The separable form can be either obtained by the Kleinman-Bylander projection [10] applied to single-projector PP's, or directly produced using Vanderbilt's procedure [2] (for single-projector PP's the two approaches are equivalent).

Unfortunately the separable form is not guaranteed to have the correct ground state (unlike the semilocal form, which, by construction, has the correct ground states): "ghost" states, having the wrong number of nodes, can appear among the occupied states or close to them, making the PP completely useless. This problem may show up in US-PP's as well.

The freedom in choosing the local part can (and usually must) be used in order to avoid the appearance of ghosts. For PW calculations it is convenient to choose as local part the highest l , because this removes more projectors ($2l + 1$ per atom) than for low l . According to Murphy's law, this is also the choice that more often gives raise

to problems, and one is forced to use a different l . Another possibility is to generate a local potential by pseudizing the AE potential.

Note that ghosts may not be visible to atomic codes based on radial integration, since the algorithm discards states with the wrong number of nodes. Difficult convergence or mysterious errors are almost invariably a sign that there is something wrong with our PP. A simple and safe way to check for the presence of a ghost is to diagonalize the Kohn-Sham hamiltonian in a basis set of spherical Bessel functions. This can be done together with transferability tests (see Sec.2.4)

2.3 Generating the pseudopotential

As a first step, one can generate AE Kohn-Sham orbitals and one-electron levels for the reference configuration. This is done by using executable `ld1.x`. You must specify in the input data:

- atomic symbol,
- electronic reference configuration,
- exchange-correlation functional (default is LDA).

A complete description of the input is contained in the documentation. For accurate AE results in heavy atoms, you may want to specify a denser radial grid in r -space than the default one. The default grid should however be good enough for PP generation.

Before you proceed, it is a good idea to verify that the atomic data you just produced actually make sense. Some kind souls have posted on the web a complete set of reference atomic data :

<http://physics.nist.gov/PhysRefData/DFTdata/>

These data have been obtained with the Vosko-Wilk-Nusair functional, that for the unpolarized case is very similar to the Perdew-Zunger LDA functional (this is the LDA default).

The generation step is also done by program `ld1.x`. One has to supply, in addition to AE data:

- a list of orbitals to be pseudized, with pseudization energies and radii,
- the filename where the newly generated PP is written,

plus a number of other optional parameters, fully described in the documentation.

2.4 Checking for transferability

A simple way to check for correctness and to get a feeling for the transferability of a PP, with little effort, is to test the results of PP and AE atomic calculations on atomic configurations differing from the starting one. The error on total energy differences between PP and AE results gives a feeling on how good the PP is. Just to give an idea: an error ~ 0.001 Ry is very good, ~ 0.01 Ry may still be acceptable. The code `ld1.x` has a “testing” mode in which it does exactly the above operation. You provide the input PP file and a number of test configurations.

You are advised to perform also the test with a basis set of spherical Bessel functions $j_l(qr)$. In addition to revealing the presence of “ghosts”, this test also gives an idea of the smoothness of the potential: the dependence of energy levels upon the cutoff in the kinetic energy is basically the same for the pseudo-atom in the basis of $j_l(qr)$ ’s and for the same pseudo-atom in a solid-state calculation using PW’s.

Another way to check for transferability is to compare AE and pseudo (PS) logarithmic derivatives, also calculated by `ld1.x`. Typically this comparison is done on the reference configuration, but not necessarily so. You should supply on input:

- the radius r_d at which logarithmic derivatives are calculated (r_d should be of the order of the ionic or covalent radius, and larger than any of the r_c ’s)
- the energy range E_{min}, E_{max} and the number of points for the plot. The energy range should cover the typical valence one-electron energy range expected in the targeted application of the PP.

The files containing logarithmic derivatives can be easily read and plotted using for instance the plotting program `gnuplot` or `xmgrace`. Sizable discrepancies between AE and PS logarithmic derivatives are a sign of trouble (unless your energy range is too large or not centered around the range of pseudization energies, of course).

Note that the above checks, based on atomic calculations only, do not replace the usual checks (convergence tests, bond lengths, etc) one has to perform in at least some simple solid-state or molecular systems before starting a serious calculation.

3 A worked example: Ti

Let us consider the Ti atom: $Z = 22$, electronic configuration: $1s^2 2s^2 2p^6 3s^2 3p^6 3d^2 4s^2$, with PBE XC functional. The input data for the AE calculation is simple:

```
&input
  atom='Ti', dft='PBE', config='[Ar] 3d2 4s2 4p0'
/
```

and yields the total energy and Kohn-Sham levels. Let us concentrate on the outermost states:

3 0	3S 1(2.00)	-4.6035	-2.3017	-62.6334
3 1	3P 1(6.00)	-2.8562	-1.4281	-38.8608
3 2	3D 1(2.00)	-0.3130	-0.1565	-4.2588
4 0	4S 1(2.00)	-0.3283	-0.1641	-4.4667
4 1	4P 1(0.00)	-0.1078	-0.0539	-1.4663

and on their spatial extension:

s(3S/3S) =	1.000000	<r> =	1.0069	<r2> =	1.1699	r(max) =	0.8702
s(3P/3P) =	1.000000	<r> =	1.0860	<r2> =	1.3907	r(max) =	0.8985
s(3D/3D) =	1.000000	<r> =	1.6171	<r2> =	3.5729	r(max) =	0.9811
s(4S/4S) =	1.000000	<r> =	3.5138	<r2> =	14.2491	r(max) =	2.9123
s(4P/4P) =	1.000000	<r> =	4.8653	<r2> =	27.9369	r(max) =	3.8227

Note that the $3d$ state has a small spatial extension, comparable to that of $3s$ and $3p$ states and much smaller than for $4s$ and $4p$ states; the $3d$ energy is instead comparable to that of $4s$ and $4p$ states and much higher than the $3s$ and $3p$ energies.. Much of the chemistry of Ti is determined by its $3d$ states. What should we do? We have the choice among several possibilities:

1. single-projector NC-PP with 4 electrons in valence ($3d^2 4s^2$), with nonlinear core correction;
2. single-projector NC-PP with 12 electrons in valence ($3s^2 3p^6 3d^2 4s^2$);
3. multiple-projector US-PP with 12 electrons in valence;
4. multiple-projector US-PP with 4 electrons in valence and nonlinear core correction;
5. ...

The PP of case 1) will be hard due to the presence of $3d$ states, and its transferability may turn out not be sufficient for all purposes; PP's for 2) will be even harder due to the presence of $3d$ and semicore $3s$ and $3p$ states; PP 3) can be made soft, but generating one is not trivial; PP 4) may suffer from insufficient transferability.

3.1 Single-projector, norm-conserving, no semicore

3.1.1 Generation

Let us start from the simplest case with the following input:

```
&input
  atom='Ti',  dft='PBE',  config='[Ar] 3d2 4s2 4p0',
  rlderiv=2.90, eminld=-2.0, emaxld=2.0, deld=0.01, nld=3,
  iswitch=3
/
&inputp
  pseudotype=1, nlcc=.true., lloc=1,
  file_pseudopw='Ti.pbe-n-rrkj.UPF'
/
3
4S 1 0 2.00  0.00 2.9 2.9
3D 3 2 2.00  0.00 1.3 1.3
4P 2 1 0.00  0.00 2.9 2.9
```

In the `&input` namelist, we specify the we want to generate a PP (`iswitch=3`) and to calculate `nld=3` logarithmic derivatives at `rlderiv=2.90` a.u. from the origin, in the energy range `eminld=-2.0` Ry to `emaxld=2.0` Ry, in energy steps `deld=0.01` Ry (note that these values will not affect PP generation). In the `&inputp` namelist, we specify the we want a single-projector, NC-PP (`pseudotype=1`), with nonlinear core correction (`nlcc=.true.`), using the $l = 1$ channel as local (`lloc=1`). The output PP

will be written in UPF format to file `Ti.pbe-n-rrkj.UPF` (following the QUANTUM ESPRESSO convention for PP names). Following the two namelists, there is a list of states used for pseudization: the 4S state, with pseudization radius $r_c = 2.9$ a.u.; the 3D state, $r_c = 1.3$ a.u.; the 4P, $r_c = 2.9$ a.u., listed as last because it is the channel to be chosen as local potential.

There is nothing magic or especially deep in the choice of the radius and energy range for logarithmic derivatives, of the local potential and of pseudization radii: it is just a reasonable guess. Running the input, one gets an error:

```
Wfc  4S  rcut= 2.883  Estimated cut-off energy=   14.82 Ry
l=    0 Node at 0.71997236
This function has    1 nodes for 0 < r <    2.883

%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%
from compute_phi : error #          1
phi has nodes before r_c
%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%
```

This means that the 4S pseudized orbitals has one node. With RRKJ pseudization (the default), this may occasionally happen. One can either choose TM pseudization (`tm=.true.`) or set a small value of $\rho(r = 0)$ (e.g. `rho0=0.001`). Let us do the latter. You should carefully look at the output, which will consists in an all-electron calculation, followed by the pseudopotential generation step, followed by a final test. In particular, notice this message about the nonlinear core correction:

```
Computing core charge for nlcc:

r > 1.73 : true rho core
r < 1.73 : rho core = a sin(br)/r    a=   2.40  b=   1.56

Integrated core pseudo-charge :    3.43
```

(this is actually not an ideal situation: the pseudization radius for the charge density should be smaller than all pseudization radii; in our case, smaller than $r_c^{(min)} = r_c^{(l=2)} = 1.3$ a.u.). Also notice messages on pseudization:

```
Wfc  4S  rcut= 2.883  Estimated cut-off energy=           5.32 Ry
Using 4 Bessel functions for this wfc, rho(0) = 0.001
This function has    0 nodes for 0 < r <    2.883

Wfc  3D  rcut= 1.296  Estimated cut-off energy=          137.82 Ry
This function has    0 nodes for 0 < r <    1.296
```

(note the large difference between the estimated cutoff for the *s* and the *d* channel! Of course, it is only the latter the “problem” one here); and look at the final consistency check:

n	l	nl	e AE (Ry)	e PS (Ry)	De AE-PS (Ry)
---	---	----	-----------	-----------	---------------

1	0	4S	1(2.00)	-0.32830	-0.32830	0.00000
3	2	3D	1(2.00)	-0.31302	-0.31302	0.00000
2	1	4P	1(0.00)	-0.10777	-0.10777	0.00000

You should get exactly 0 (within numerical accuracy) in the columnn at the right.


As a further check, let's have a look at the logarithmic derivatives and at pseudized Kohn-Sham orbitals. Logarithmic derivatives are written to files `ld1.dlog` and `ld1ps.dlog`, for AE and PS calculations respectively (file names can be changed using variable `prefix`). They can be plotted using for instance `gnuplot` and the following commands:

```
plot [-2:2][-20:20] 'ld1.dlog' u 1:2 w l lt 1, 'ld1.dlog' u 1:3 w l lt 2, \
                    'ld1.dlog' u 1:4 w l lt 3, 'ld1ps.dlog' u 1:2 lt 1, \
                    'ld1ps.dlog' u 1:3      lt 2, 'ld1ps.dlog' u 1:4 lt 3
```

PS orbitals and the corresponding AE ones are written to file `ld1ps.wfc` (PS on the left, AE on the right). They can be plotted using the following commands:

```
plot [0:5] 'ld1ps.wfc' u 1:2 lt 1      , 'ld1ps.wfc' u 1:3 lt 3      , \
            'ld1ps.wfc' u 1:4 lt 2      , 'ld1ps.wfc' u 1:5 lt 1 w l, \
            'ld1ps.wfc' u 1:6 lt 3 w l, 'ld1ps.wfc' u 1:7 lt 2 w l
```

One gets the following plots (AE=lines, PS=points; `lt 1`=red=*s*; `lt 2`=green=*p*; `lt 3`=blue=*d*; note that in the files, orbitals are ordered as given in input, logarithmic derivatives as *s*, *p*, *d*).



We observe that our PP seems to reproduce fairly well the logarithmic derivatives, with deviations appearing only at relatively high (> 1 Ry) energies. AE and PS orbitals match very well beyond the pseudization radii; the 3*d* orbital is slightly deformed, because we have chosen a relatively large $r_c^{(l=2)} = 1.3$ a.u.. It is easy to verify that a smaller $r_c^{(l=2)}$ yields a better 3*d* PS orbital, but also a harder *d* potential: e.g., for $r_c^{(l=2)} = 1.0$ a.u., you get

```
Wfc    3D  rcut= 1.009  Estimated cut-off energy=      225.64 Ry
```

Before proceeding, it is wise to verify whether our PP has “ghosts”. Let us prepare the following input for the testing phase (note the variable `iswitch=2` and the `&test` namelist):

```

&input
  atom='Ti',  dft='PBE',  config='[Ar] 3d2 4s2 4p0',
  iswitch=2
/
&test
  file_pseudo='Ti.pbe-n-rrkj.UPF',
  nconf=1, configts(1)='3d2 4s2 4p0',
  ecutmin=50, ecutmax=200, decut=50
/

```

This will solve the Kohn-Sham equation for the PP read from `file_pseudo`, for a single valence configuration (`nconf=1`) listed in `configts(1)` (the ground state in this case), using a base of spherical waves whose cutoff (in Ry) ranges from `ecutmin` to `ecutmax` in steps of `decut`. The initial part of the output looks good, but let us look at the test with spherical waves, towards the end:

```

Cutoff (Ry) : 200.0

                N = 1          N = 2          N = 3
E(L=0) =      -0.7483 Ry   -0.3282 Ry   -0.0042 Ry
E(L=1) =      -0.1077 Ry    0.0192 Ry    0.0630 Ry
E(L=2) =      -0.2961 Ry    0.0304 Ry    0.0654 Ry

```

The lowest levels found in this way should be the same¹ as those calculated from radial integration (see above). This is true for the *4p* state (-0.1077 Ry), for the *3d* state (-0.2961 Ry vs -0.31302 Ry, see footnote), for the *4s* state (-0.3282 Ry)....but note the spurious *4s* level at -0.7483 Ry! Our PP has a ghost and is unusable.

What should be do now? we may try to change the definition of the local potential. We had chosen $l = 1$, let us try $l = 2$ and $l = 0$. The former has the same pathology, the latter has no ghosts. So our data for PP generation are as follows:

```

&input
  atom='Ti',  dft='PBE',  config='[Ar] 3d2 4s2 4p0',
  rlderiv=2.90, eminld=-2.0, emaxld=2.0, deld=0.01, nld=3,
  iswitch=3
/
&inputp
  pseudotype=1, nlcc=.true., lloc=0,
  file_pseudopw='Ti.pbe-n-rrkj.UPF',
/
3
4P 2 1 0.00 0.00 2.9 2.9
3D 3 2 2.00 0.00 1.3 1.3
4S 1 0 2.00 0.00 2.9 2.9

```

(note `lloc=0` and the *4s* state at the end of the list). Let us plot again logarithmic derivatives and orbitals (they look quite the same as before) and run again the test with spherical waves. We get (see the last section in the output):

¹actually there are numerical differences, especially large for localized states like *3d*, whose origin is under investigation

Cutoff (Ry) :	50.0		
	N = 1	N = 2	N = 3
E(L=0) =	-0.3282 Ry	-0.0049 Ry	0.0361 Ry
E(L=1) =	-0.1077 Ry	0.0192 Ry	0.0630 Ry
E(L=2) =	-0.1469 Ry	0.0311 Ry	0.0682 Ry

Cutoff (Ry) :	100.0		
	N = 1	N = 2	N = 3
E(L=0) =	-0.3282 Ry	-0.0049 Ry	0.0361 Ry
E(L=1) =	-0.1077 Ry	0.0192 Ry	0.0630 Ry
E(L=2) =	-0.2959 Ry	0.0303 Ry	0.0652 Ry

Cutoff (Ry) :	150.0		
	N = 1	N = 2	N = 3
E(L=0) =	-0.3282 Ry	-0.0049 Ry	0.0361 Ry
E(L=1) =	-0.1077 Ry	0.0192 Ry	0.0630 Ry
E(L=2) =	-0.2961 Ry	0.0303 Ry	0.0652 Ry

This time the first column yields (with a small discrepancy for $3d$) the expected levels, and only those levels. It is wise to inspect the second column as well for absence of suspiciously low levels: ghosts may appear also as spurious excited states close to occupied states. Note how bad the energy for the $3d$ level is at 50 Ry. At 100 Ry however we are close to convergence and at 150 Ry well converged, in agreement with the estimate given during the PP generation (138 Ry).

We have now our first candidate (i.e. not surely wrong) PP. In order to 1) verify if it really does the job, 2) quantify its transferability, 3) quantify its hardness, and 4) improve it, if possible, we need to perform some more testing.

3.1.2 Testing

As a first idea of how good our PP is, let us verify how it behaves on different electronic configuration. The code allows to test several configurations in the following way:

```
&input
  atom='Ti',  dft='PBE',  config='[Ar] 3d2 4s2 4p0',
  iswitch=2
/
&test
  file_pseudo='Ti.pbe-n-rrkj.UPF',
  nconf=9
  configts(1)='3d2 4s2 4p0'
  configts(2)='3d2 4s1 4p1'
  configts(3)='3d2 4s1 4p0'
  configts(4)='3d2 4s0 4p0'
  configts(5)='3d1 4s2 4p1'
  configts(6)='3d1 4s2 4p0'
  configts(7)='3d1 4s1 4p0'
  configts(8)='3d1 4s0 4p0'
```



```
configs(9)='3d0 4s0 4p0'
```

/

here we have chosen 9 different valence configurations (the corresponding AE configurations are obtained by superimposing `configs` to core states in `config`). Some of them are neutral, some are ionic, the first five leave the $3d$ states unchanged, the last one is a completely ionized Ti^{4+} . For each configuration, the code writes results (e.g. orbitals) into files `ld1N.*` and `ld1psN.*`, where N is the index of the configuration. A summary is written to file `ld1.test`. For the first configuration, AE and PS eigenvalues and total energies are written:

```

3 2      3D   1( 2.00)      -0.31302      -0.31302      0.00000
1 0      4S   1( 2.00)      -0.32830      -0.32830      0.00000
2 1      4P   1( 0.00)      -0.10777      -0.10777      0.00000
Etot =    -1707.131006 Ry,      -853.565503 Ha,    -23226.698556 eV
Etotps =     -9.748745 Ry,        -4.874372 Ha,     -132.638416 eV
```

(AE and PS eigenvalues are in this case the same, since this is the reference configuration used to build the PP). For the following configurations, AE and PS eigenvalues, plus total energy *differences*² wrt configuration 1 are printed:

```

3 2      3D   1( 2.00)      -0.40319      -0.40457      0.00138
1 0      4S   1( 1.00)      -0.38394      -0.38420      0.00026
2 1      4P   1( 1.00)      -0.15248      -0.15237     -0.00011
dEtot_ae =           0.226061 Ry
dEtot_ps =           0.226250 Ry,    Delta E=       -0.000189 Ry
```

The discrepancy between AE and PS energy differences (in this case, wrt the ground state) as well as the discrepancies in AE and PS eigenvalues, are a measure of how transferrable a PP is. In this case, the AE-PS discrepancy on $\delta E = E(4s^1 4p^1 3d^2) - E(4s^2 4p^0 3d^2)$ (look at Delta E) is quite small, < 0.2 mRy, while the maximum discrepancy of the eigenvalues (rightmost column) ~ 1 mRy. These are very good results. Unfortunately this is also a configuration that doesn't differ much from the reference one. Let us see the other cases:

```

3 2      3D   1( 2.00)      -0.83550      -0.83256     -0.00295
1 0      4S   1( 1.00)      -0.76075      -0.76163      0.00088
2 1      4P   1( 0.00)      -0.48549      -0.48617      0.00068
dEtot_ae =           0.539968 Ry
dEtot_ps =           0.540344 Ry,    Delta E=       -0.000376 Ry

3 2      3D   1( 2.00)      -1.44648      -1.44538     -0.00110
1 0      4S   1( 0.00)      -1.24186      -1.24652      0.00465
2 1      4P   1( 0.00)      -0.91224      -0.91599      0.00375
dEtot_ae =           1.537516 Ry
dEtot_ps =           1.540285 Ry,    Delta E=       -0.002769 Ry
```

²Reminder: absolute PS total energies depend upon the specific PP! Only energy differences are significant.


3 2	3D	1(1.00)	-0.68514	-0.74236	0.05722
1 0	4S	1(2.00)	-0.45729	-0.45802	0.00073
2 1	4P	1(1.00)	-0.18855	-0.18471	-0.00383
dEtot_ae =			0.343391 Ry		
dEtot_ps =			0.371650 Ry,	Delta E=	-0.028259 Ry
3 2	3D	1(1.00)	-1.16621	-1.21438	0.04817
1 0	4S	1(2.00)	-0.87720	-0.87620	-0.00100
2 1	4P	1(0.00)	-0.56807	-0.56137	-0.00670
dEtot_ae =			0.716203 Ry		
dEtot_ps =			0.739110 Ry,	Delta E=	-0.022907 Ry
3 2	3D	1(1.00)	-1.82248	-1.87471	0.05223
1 0	4S	1(1.00)	-1.39447	-1.39936	0.00489
2 1	4P	1(0.00)	-1.03942	-1.03465	-0.00476
dEtot_ae =			1.848995 Ry		
dEtot_ps =			1.873240 Ry,	Delta E=	-0.024245 Ry
3 2	3D	1(1.00)	-2.54976	-2.61959	0.06983
1 0	4S	1(0.00)	-1.94361	-1.96745	0.02383
2 1	4P	1(0.00)	-1.53584	-1.54419	0.00835
dEtot_ae =			3.518170 Ry		
dEtot_ps =			3.554733 Ry,	Delta E=	-0.036564 Ry
3 2	3D	1(0.00)	-3.84145	-3.95251	0.11106
1 0	4S	1(0.00)	-2.73793	-2.81405	0.07612
2 1	4P	1(0.00)	-2.25938	-2.28768	0.02831
dEtot_ae =			6.699594 Ry		
dEtot_ps =			6.831938 Ry,	Delta E=	-0.132344 Ry

It is evident that configurations with $3d^2$ occupancy are well reproduced, with errors on total energy differences < 3 mRy and on eigenvalues < 5 mRy. Configurations with different $3d$ occupancy, however, have errors one order of magnitude higher. For the extreme case of Ti^{4+} , the error is ~ 0.1 Ry.

In order to better understand what is going on, let us have a look at the AE vs PS orbitals and logarithmic derivatives for configuration 9 (i.e. for the bare PP). Let us add a line like this:

```
rlderiv=2.90, eminld=-4.0, emaxld=0.0, deld=0.01, nld=3,
```

and plot files `ld19ps.wfc`, `ld19.dlog`, `ld19ps.dlog` using `gnuplot` as above :



Both the orbitals and the logarithmic derivatives (note the different energy range) start to exhibit some visible discrepancy now.

One can try to fiddle with all generation parameters, better if one at the time, to see whether things improve. Curiously enough, the pseudization radius for the core correction, which in principle should be as small as possible, seems to improve things if pushed slightly outwards (try `rcore=2.0`). Also surprisingly, a smaller pseudization radius for the 3d state, 0.9 or 1.0 a.u., doesn't bring any visible improvement to transferability (but it increases a lot the required cutoff!). Changing the pseudization radii for 4s and 4p states doesn't affect much the results.

A different local potential – a pseudized version of the total self-consistent potential – can be chosen by setting `lloc=-1` and setting `rcloc` to the desired pseudization radius (a.u.). For small `rcloc` ghosts re-appear; `rcloc=2.9` yields slightly better total energy differences but slightly worse eigenvalues. Note that the PP so generated will also have a *s* projector, while the previous ones had only *p* and *d* projectors.

One could also generate the PP from a different electronic configuration. Since Ti tends to lose rather than to attract electrons, it will be more easily found in a ionized state than in the neutral one. One might for instance use the electronic configuration of the Bachelet-Hamann-Schlüter paper[4]: $3d^2 4s^{0.75} 4p^{0.25}$. This however doesn't seem to improve much.

Finally we end up with these generation data:

```
&input
  atom='Ti',  dft='PBE',  config='[Ar] 3d2 4s2 4p0',
  iswitch=3
/
&inputp
  pseudotype=1, nlcc=.true., rcore=2.0, lloc=0,
  file_pseudopw='Ti.pbe-n-rrkj.UPF'
/
3
4P 2 1 0.00  0.00 2.9 2.9
3D 3 2 2.00  0.00 1.3 1.3
4S 1 0 2.00  0.00 2.9 2.9
```

3.2 Single-projector, norm-conserving, with semicore states

The results of transferability tests suggest that a Ti PP with only $3d$, $4s$, $4p$ states have limited transferability to cases with different $3d$ configurations. In order to improve it, a possible way is to put semicore $3s$ and $3p$ states in valence. The maximum for those states (0.87 a.u. and 0.90 a.u. respectively) is in the same range as for $3d$ (0.98 a.u.). Let us try thus the following:

```
&input
  atom='Ti', dft='PBE', config='[Ar] 3d2 4s2 4p0',
  rlderiv=2.90, eminld=-4.0, emaxld=2.0, deld=0.01, nld=3,
  iswitch=3
/
&inputp
  pseudotype=1, rho0=0.001, ...
  file_pseudopw='Ti.pbe-sp-rrkj.UPF'
/
3
3S 1 0 2.00 0.00 1.1 1.1
3P 2 1 6.00 0.00 1.2 1.2
3D 3 2 2.00 0.00 1.3 1.3
&test
  configts(1)='3s2 3p6 3d2 4s2 4p0',
/
```

Note the presence of the `&test` namelist: it is used in this context to supply the electronic valence configuration, to be used for unscreening. As a first step, we do not include the core correction. In place of the dots we should specify the local reference potential. If we use `lloc=-1` with large values of `rcloc`, (comparable to pseudization radii for the previous case) we get all kinds of mysterious errors:

```
from compute_chi : error #          1
n is too large
```

for `rcloc=2.5`, while `rcloc=2.7` produces an equally mysterious

```
from run_pseudo : error #          1
Errors in PS-KS equation
```

while smaller values (e.g. 1.5) lead to other errors:

```
WARNING! Expected number of nodes: 0 = 2-1-1, number of nodes found: 1.
```

Even if the code doesn't stop, the presence of such messages is a signal of something going wrong in the generation algorithm. With some more experiments, though, one finds that `rcloc=1.3` yields a good potential. We still have other choices. In this case, d as reference potential: `lloc=2`, seems to work as well (and produces a PP with less projectors: only s and p). The generation algorithm in the latter case yields these results for Kohn-Sham energies:

n l	nl		e AE (Ry)	e PS (Ry)	De AE-PS (Ry)
1 0	3S	1(2.00)	-4.60347	-4.60348	0.00001
2 1	3P	1(6.00)	-2.85621	-2.85623	0.00002
3 2	3D	1(2.00)	-0.31302	-0.31301	-0.00001
2 0	4S	1(2.00)	-0.32830	-0.32892	0.00062
3 1	4P	1(0.00)	-0.10777	-0.10732	-0.00045

Note that the $3s$, $3p$, $3d$ levels should be the same by construction (the difference is numerical noise); the $4s$ and $4p$ levels are not guaranteed to be the same. The fact that they are, to a very good degree, is very reassuring. A look at the orbitals will reveal that $3s, 3p, 3d$ are nodeless, $4s$ and $4p$ have one node. The spherical wave basis set confirms the absence of ghosts:

Cutoff (Ry) :	50.0			
		N = 1	N = 2	N = 3
E(L=0) =	-4.5385 Ry	-0.3263 Ry	-0.0047 Ry	
E(L=1) =	-2.8427 Ry	-0.1071 Ry	0.0193 Ry	
E(L=2) =	-0.1511 Ry	0.0311 Ry	0.0685 Ry	

Cutoff (Ry) :	100.0			
		N = 1	N = 2	N = 3
E(L=0) =	-4.5883 Ry	-0.3279 Ry	-0.0048 Ry	
E(L=1) =	-2.8547 Ry	-0.1073 Ry	0.0193 Ry	
E(L=2) =	-0.2918 Ry	0.0303 Ry	0.0649 Ry	

Cutoff (Ry) :	150.0			
		N = 1	N = 2	N = 3
E(L=0) =	-4.5899 Ry	-0.3280 Ry	-0.0048 Ry	
E(L=1) =	-2.8549 Ry	-0.1073 Ry	0.0193 Ry	
E(L=2) =	-0.2936 Ry	0.0303 Ry	0.0649 Ry	

Note that for $l = 0$ the first ($N = 1$) level is the $3s$ level, the second ($N = 2$) level is the $4s$ level, and the like for $l = 1$. Let us now repeat the testing on the nine selected configurations as for the 4-electron PP. You will have to add $3s^2 3p^6$ to all test configurations `configs`. Let us see check the errors on total energy differences:

```
$ grep Delta ld1.test
dEtot_ps =      0.227291 Ry,   Delta E=      -0.001230 Ry
dEtot_ps =      0.540886 Ry,   Delta E=      -0.000918 Ry
dEtot_ps =      1.540155 Ry,   Delta E=      -0.002640 Ry
dEtot_ps =      0.343314 Ry,   Delta E=       0.000077 Ry
dEtot_ps =      0.715061 Ry,   Delta E=       0.001142 Ry
dEtot_ps =      1.849816 Ry,   Delta E=      -0.000820 Ry
dEtot_ps =      3.522904 Ry,   Delta E=      -0.004735 Ry
dEtot_ps =      6.702626 Ry,   Delta E=      -0.003032 Ry
```

Energy differences are reproduced with an error that does not exceed a few mRy (see column at the rhs). Eigenvalues are also well reproduced, e.g.:

1	0	3S	1(2.00)	-8.37382	-8.37230	-0.00152
2	1	3P	1(6.00)	-6.57173	-6.57195	0.00021
3	2	3D	1(0.00)	-3.84145	-3.83518	-0.00627
2	0	4S	1(0.00)	-2.73793	-2.74985	0.01192
3	1	4P	1(0.00)	-2.25938	-2.25525	-0.00412

although errors may reach 0.01 Ry (still one order of magnitude better than what we get with the previous 4-electron PP). The price to pay is the presence of more electrons in the valence.

3.3 Testing in molecules and solids

Even if our PP looks good (or not too bad) on paper based on the results of atomic calculations, it is always a good idea to test it in simple molecular or solid-state systems, for which all-electron data (i.e. calculations performed with the same XC functional but without PP's, such as e.g. FLAPW, LMTO, Quantum Chemistry calculations) is available. The comparison with experiments is of course interesting, but the goal of PP's is (at least in principle) to reproduce AE data, not to improve DFT.

A Atomic Calculations

A.1 Nonrelativistic case

Let us assume that the charge density $n(r)$ and the potential $V(r)$ are spherically symmetric. The Kohn-Sham (KS) equation:

$$\left(-\frac{\hbar^2}{2m}\nabla^2 + V(r) - \epsilon\right)\psi(\mathbf{r}) = 0 \quad (1)$$

can be written in spherical coordinates. We write the wavefunctions as

$$\psi(\mathbf{r}) = \left(\frac{R_{nl}(r)}{r}\right) Y_{lm}(\hat{\mathbf{r}}), \quad (2)$$

where n is the main quantum number $l = n - 1, n - 2, \dots, 0$ is angular momentum, $m = l, l - 1, \dots, -l + 1, -l$ is the projection of the angular momentum on some axis. The radial KS equation becomes:

$$\begin{aligned} &\left(-\frac{\hbar^2}{2m} \frac{1}{r} \frac{d^2 R_{nl}(r)}{dr^2} + (V(r) - \epsilon) \frac{1}{r} R_{nl}(r)\right) Y_{lm}(\hat{\mathbf{r}}) \\ &- \frac{\hbar^2}{2m} \left(\frac{1}{\sin\theta} \frac{\partial}{\partial\theta} \left(\sin\theta \frac{\partial Y_{lm}(\hat{\mathbf{r}})}{\partial\theta}\right) + \frac{1}{\sin^2\theta} \frac{\partial^2 Y_{lm}(\hat{\mathbf{r}})}{\partial\phi^2}\right) \frac{1}{r^3} R_{nl}(r) = 0. \end{aligned} \quad (3)$$

This yields an angular equation for the spherical harmonics $Y_{lm}(\hat{\mathbf{r}})$:

$$-\left(\frac{1}{\sin\theta} \frac{\partial}{\partial\theta} \left(\sin\theta \frac{\partial Y_{lm}(\hat{\mathbf{r}})}{\partial\theta}\right) + \frac{1}{\sin^2\theta} \frac{\partial^2 Y_{lm}(\hat{\mathbf{r}})}{\partial\phi^2}\right) = l(l+1) Y_{lm}(\hat{\mathbf{r}}) \quad (4)$$

and a radial equation for the radial part $R_{nl}(r)$:

$$-\frac{\hbar^2}{2m} \frac{d^2 R_{nl}(r)}{dr^2} + \left(\frac{\hbar^2}{2m} \frac{l(l+1)}{r^2} + V(r) - \epsilon\right) R_{nl}(r) = 0. \quad (5)$$

The charge density is given by

$$n(r) = \sum_{nlm} \Theta_{nl} \left| \frac{R_{nl}(r)}{r} Y_{lm}(\hat{\mathbf{r}}) \right|^2 = \sum_{nl} \Theta_{nl} \frac{R_{nl}^2(r)}{4\pi r^2} \quad (6)$$

where Θ_{nl} are the occupancies ($\Theta_{nl} \leq 2l + 1$) and it is assumed that the occupancies of m are such as to yield a spherically symmetric charge density (which is true only for closed shell atoms).

A.1.1 Useful formulae

Gradient in spherical coordinates (r, θ, ϕ) :

$$\nabla\psi = \left(\frac{\partial\psi}{\partial r}, \frac{1}{r} \frac{\partial\psi}{\partial\theta}, \frac{1}{r\sin\theta} \frac{\partial\psi}{\partial\phi} \right) \quad (7)$$

Laplacian in spherical coordinates:

$$\nabla^2\psi = \frac{1}{r} \frac{\partial^2}{\partial r^2}(r\psi) + \frac{1}{r^2\sin\theta} \frac{\partial}{\partial\theta} \left(\sin\theta \frac{\partial\psi}{\partial\theta} \right) + \frac{1}{r^2\sin^2\theta} \frac{\partial^2\psi}{\partial\phi^2} \quad (8)$$

A.2 Fully relativistic case

The relativistic KS equations are Dirac-like equations for a spinor with a “large” $R_{nlj}(r)$ and a “small” $S_{nlj}(r)$ component:

$$c \left(\frac{d}{dr} + \frac{\kappa}{r} \right) R_{nlj}(r) = (2mc^2 - V(r) + \epsilon) S_{nlj}(r) \quad (9)$$

$$c \left(\frac{d}{dr} - \frac{\kappa}{r} \right) S_{nlj}(r) = (V(r) + \epsilon) R_{nlj}(r) \quad (10)$$

where j is the total angular momentum ($j = 1/2$ if $l = 0$, $j = l + 1/2, l - 1/2$ otherwise); $\kappa = -2(j - l)(j + 1/2)$ is the Dirac quantum number ($\kappa = -1$ is $l = 0$, $\kappa = -l - 1, l$ otherwise); and the charge density is given by

$$n(r) = \sum_{nlj} \Theta_{nlj} \frac{R_{nlj}^2(r) + S_{nlj}^2(r)}{4\pi r^2}. \quad (11)$$

A.3 Scalar-relativistic case

The full relativistic KS equations is be transformed into an equation for the large component only and averaged over spin-orbit components. In atomic units (Rydberg: $\hbar = 1, m = 1/2, e^2 = 2$):

$$\begin{aligned} -\frac{d^2 R_{nl}(r)}{dr^2} + \left(\frac{l(l+1)}{r^2} + M(r) (V(r) - \epsilon) \right) R_{nl}(r) \\ - \frac{\alpha^2}{4M(r)} \frac{dV(r)}{dr} \left(\frac{dR_{nl}(r)}{dr} + \langle \kappa \rangle \frac{R_{nl}(r)}{r} \right) = 0, \end{aligned} \quad (12)$$

where $\alpha = 1/137.036$ is the fine-structure constant, $\langle \kappa \rangle = -1$ is the degeneracy-weighted average value of the Dirac's κ for the two spin-orbit-split levels, $M(r)$ is defined as

$$M(r) = 1 - \frac{\alpha^2}{4} (V(r) - \epsilon). \quad (13)$$

The charge density is defined as in the nonrelativistic case:

$$n(r) = \sum_{nl} \Theta_{nl} \frac{R_{nl}^2(r)}{4\pi r^2}. \quad (14)$$

A.4 Numerical solution

The radial (scalar-relativistic) KS equation is integrated on a radial grid. It is convenient to have a denser grid close to the nucleus and a coarser one far away. Traditionally a logarithmic grid is used: $r_i = r_0 \exp(i\Delta x)$. With this grid, one has

$$\int_0^\infty f(r) dr = \int_0^\infty f(x) r(x) dx \quad (15)$$

and

$$\frac{df(r)}{dr} = \frac{1}{r} \frac{df(x)}{dx}, \quad \frac{d^2 f(r)}{dr^2} = -\frac{1}{r^2} \frac{df(x)}{dx} + \frac{1}{r^2} \frac{d^2 f(x)}{dx^2}. \quad (16)$$

We start with a given self-consistent potential V and a trial eigenvalue ϵ . The equation is integrated from $r = 0$ outwards to r_t , the outermost classical (nonrelativistic for simplicity) turning point, defined by $l(l+1)/r_t^2 + (V(r_t) - \epsilon) = 0$. In a logarithmic grid (see above) the equation to solve becomes:

$$\begin{aligned} \frac{1}{r^2} \frac{d^2 R_{nl}(x)}{dx^2} &= \frac{1}{r^2} \frac{dR_{nl}(x)}{dx} + \left(\frac{l(l+1)}{r^2} + M(r)(V(r) - \epsilon) \right) R_{nl}(r) \\ &\quad - \frac{\alpha^2}{4M(r)} \frac{dV(r)}{dr} \left(\frac{1}{r} \frac{dR_{nl}(x)}{dx} + \langle \kappa \rangle \frac{R_{nl}(r)}{r} \right). \end{aligned} \quad (17)$$

This determines $d^2 R_{nl}(x)/dx^2$ which is used to determine $dR_{nl}(x)/dx$ which in turn is used to determine $R_{nl}(r)$, using predictor-corrector or whatever classical integration method. $dV(r)/dr$ is evaluated numerically from any finite difference method. The series is started using the known (?) asymptotic behavior of $R_{nl}(r)$ close to the nucleus (with ionic charge Z)

$$R_{nl}(r) \simeq r^\gamma, \quad \gamma = \frac{l\sqrt{l^2 - \alpha^2 Z^2} + (l+1)\sqrt{(l+1)^2 - \alpha^2 Z^2}}{2l+1}. \quad (18)$$

The number of nodes is counted. If there are too few (many) nodes, the trial eigenvalue is increased (decreased) and the procedure is restarted until the correct number $n-l-1$ of nodes is reached. Then a second integration is started inward, starting from a suitably large $r \sim 10r_t$ down to r_t , using as a starting point the asymptotic behavior of $R_{nl}(r)$ at large r :

$$R_{nl}(r) \simeq e^{-k(r)r}, \quad k(r) = \sqrt{\frac{l(l+1)}{r^2} + (V(r) - \epsilon)}. \quad (19)$$

The two pieces are continuously joined at r_t and a correction to the trial eigenvalue is estimated using perturbation theory (see below). The procedure is iterated to self-consistency.

The perturbative estimate of correction to trial eigenvalues is described in the following for the nonrelativistic case (it is not worth to make relativistic corrections on top of a correction). The trial eigenvector $R_{nl}(r)$ will have a cusp at r_t if the trial eigenvalue is not a true eigenvalue:

$$A = \frac{dR_{nl}(r_t^+)}{dr} - \frac{dR_{nl}(r_t^-)}{dr} \neq 0. \quad (20)$$

Such discontinuity in the first derivative translates into a $\delta(r_t)$ in the second derivative:

$$\frac{d^2 R_{nl}(r)}{dr^2} = \frac{d^2 \tilde{R}_{nl}(r)}{dr^2} + A\delta(r - r_t) \quad (21)$$

where the tilde denotes the function obtained by matching the second derivatives in the $r < r_t$ and $r > r_t$ regions. This means that we are actually solving a different problem in which $V(r)$ is replaced by $V(r) + \Delta V(r)$, given by

$$\Delta V(r) = -\frac{\hbar^2}{2m} \frac{A}{R_{nl}(r_t)} \delta(r - r_t). \quad (22)$$

The energy difference between the solution to such fictitious potential and the solution to the real potential can be estimated from perturbation theory:

$$\Delta\epsilon_{nl} = -\langle\psi|\Delta V|\psi\rangle = \frac{\hbar^2}{2m} R_{nl}(r_t) A. \quad (23)$$

B Equations for the Troullier-Martins method

We assume a pseudowavefunction R^{ps} having the following form:

$$R^{ps}(r) = r^{l+1} e^{p(r)} \quad r \leq r_c \quad (24)$$

$$R^{ps}(r) = R(r) \quad r \geq r_c \quad (25)$$

where

$$p(r) = c_0 + c_2 r^2 + c_4 r^4 + c_6 r^6 + c_8 r^8 + c_{10} r^{10} + c_{12} r^{12}. \quad (26)$$

On this pseudowavefunction we impose the norm conservation condition:

$$\int_{r < r_c} (R^{ps}(r))^2 dr = \int_{r < r_c} (R(r))^2 dr \quad (27)$$

and continuity conditions on the wavefunction and its derivatives up to order four at the matching point:

$$\frac{d^n R^{ps}(r_c)}{dr^n} = \frac{d^n R(r_c)}{dr^n}, \quad n = 0, \dots, 4 \quad (28)$$

- Continuity of the wavefunction:

$$R^{ps}(r_c) = r_c^{l+1} e^{p(r_c)} = R(r_c) \quad (29)$$

$$p(r_c) = \log \frac{R(r_c)}{r_c^{l+1}} \quad (30)$$

- Continuity of the first derivative of the wavefunction:

$$\frac{dR^{ps}(r)}{dr} = (l+1)r^l e^{p(r)} + r^{l+1} e^{p(r)} p'(r) = \frac{l+1}{r} R^{ps}(r) + p'(r) R^{ps}(r) \quad (31)$$

that is

$$p'(r_c) = \frac{dR(r_c)}{dr} \frac{1}{R^{ps}(r_c)} - \frac{l+1}{r_c}. \quad (32)$$

- Continuity of the second derivative of the wavefunction:

$$\begin{aligned}
\frac{d^2 R^{ps}(r)}{d^2 r} &= \frac{d}{dr} ((l+1)r^l e^{p(r)} + r^{l+1} e^{p(r)} p'(r)) \\
&= l(l+1)r^{l-1} e^{p(r)} + 2(l+1)r^l e^{p(r)} p'(r) + r^{l+1} e^{p(r)} [p'(r)]^2 + r^{l+1} e^{p(r)} p''(r) \\
&= \left(\frac{l(l+1)}{r^2} + \frac{2(l+1)}{r} p'(r) + [p'(r)]^2 + p''(r) \right) r^{l+1} e^{p(r)}.
\end{aligned} \tag{33}$$

From the radial Schrödinger equation:

$$\frac{d^2 R^{ps}(r)}{dr^2} = \left(\frac{l(l+1)}{r^2} + \frac{2m}{\hbar^2} (V(r) - \epsilon) \right) R^{ps}(r) \tag{34}$$

that is

$$p''(r_c) = \frac{2m}{\hbar^2} (V(r_c) - \epsilon) - 2 \frac{l+1}{r_c} p'(r_c) - [p'(r_c)]^2 \tag{35}$$

- Continuity of the third and fourth derivatives of the wavefunction. This is assured if the third and fourth derivatives of $p(r)$ are continuous. By direct derivation of the expression of $p''(r)$:

$$p'''(r_c) = \frac{2m}{\hbar^2} V'(r_c) + 2 \frac{l+1}{r_c^2} p'(r_c) - 2 \frac{l+1}{r_c} p''(r_c) - 2 p'(r_c) p''(r_c) \tag{36}$$

$$\begin{aligned}
p''''(r_c) &= \frac{2m}{\hbar^2} V''(r_c) - 4 \frac{l+1}{r_c^3} p'(r_c) + 4 \frac{l+1}{r_c^2} p''(r_c) \\
&\quad - 2 \frac{l+1}{r_c} p'''(r_c) - 2 [p''(r_c) p''(r_c)]^2 - 2 p'(r_c) p'''(r_c)
\end{aligned} \tag{37}$$

The additional condition: $V''(0) = 0$ is imposed. The screened potential is

$$V(r) = \frac{\hbar^2}{2m} \left(\frac{1}{R^{ps}(r)} \frac{d^2 R^{ps}(r)}{dr^2} - \frac{l(l+1)}{r^2} \right) + \epsilon \tag{38}$$

$$= \frac{\hbar^2}{2m} \left(2 \frac{l+1}{r} p'(r) + [p'(r)]^2 + p''(r) \right) + \epsilon \tag{39}$$

Keeping only lower-order terms in r :

$$V(r) \simeq \frac{\hbar^2}{2m} \left(2 \frac{l+1}{r} (2c_2 r + 4c_4 r^3) + 4c_2^2 r^2 + 2c_2 + 12c_4 r^2 \right) + \epsilon \tag{40}$$

$$= \frac{\hbar^2}{2m} (2c_2(2l+3) + ((2l+5)c_4 + c_2^2) r^2) + \epsilon. \tag{41}$$

The additional constraint is:

$$(2l+5)c_4 + c_2^2 = 0. \tag{42}$$

References

- [1] D.R. Hamann, M. Schlüter, and C. Chiang, Phys. Rev. Lett. **43**, 1494 (1979).
- [2] D. Vanderbilt, Phys. Rev. B **47**, 10142 (1993).
- [3] P. E. Blöchl, Phys. Rev. B **50**, 17953 (1994).
- [4] G.B. Bachelet, D.R. Hamann and M. Schlüter, Phys. Rev. B **26**, 4199 (1982).
- [5] X. Gonze, R. Stumpf, and M. Scheffler, Phys. Rev. B **44**, 8503 (1991).
- [6] S. Goedecker, M. Teter, and J. Hutter, Phys. Rev. B **54**, 1703 (1996).
- [7] N. Troullier and J.L. Martins, Phys. Rev. B **43**, 1993 (1991).
- [8] M.Fuchs and M. Scheffler, Comput. Phys. Commun. **119**, 67 (1999).
- [9] A. M. Rappe, K. M. Rabe, E. Kaxiras, and J. D. Joannopoulos, Phys. Rev. B **41**, 1227 (1990) (erratum: Phys. Rev. B **44**, 13175 (1991)).
- [10] L. Kleinman and D.M. Bylander, Phys. Rev. Lett. **48**, 1425 (1982).
- [11] S.G. Louie, S. Froyen, and M.L. Cohen, Phys. Rev. B **26**, 1738 (1982).
- [12] S.H. Wei and A. Zunger, Phys. Rev. B **37**, 8958 (1987).